CSC358 Week 6

Logistics

- Assignment 2 due Feb 18
- Next week is reading week
 - no lecture, no tutorial, no office hours
- The week after reading week
 - Midterm in class
 - Coverage: everything before the reading week
 - lecture, tutorials, assignments
 - Aid: one double-sided 8.5x11 sheet
 - Bring your T-card
- Past test posted on the course website

Logistics

- Pre-test office hours
 - Michael: Monday, Feb 24, 4:30 6 PM
 - Larry: Tuesday, Feb 25, 12:30 2 PM

Outline

- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer

- 3.5 connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control

Principles of congestion control

congestion:


- informally: "too many sources sending too much data too fast for network to handle"
- different from flow control!
- manifestations:
 - lost packets (buffer overflow at routers)
 - long delays (queueing in router buffers)
- a top-10 problem!

Causes/costs of congestion

Host A


original data: λ_{in} two senders, two receivers one router, infinite buffers output link capacity: R

no retransmission



Host B

maximum per-connection throughput: R/2



large delays as arrival rate, λ_{in} , approaches capacity

unlimited shared output link buffers

throughput: λ_{out}

Outline


- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer

- 3.5 connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control

TCP congestion control: additive increase multiplicative decrease

- approach: sender increases transmission rate (window size), probing for usable bandwidth, until loss occurs
 - additive increase: increase cwnd by 1 MSS every RTT until loss detected
 - multiplicative decrease: cut cwnd in half after loss


AIMD saw tooth behavior: probing for bandwidth



cwnd: congestion window, number of unACKed bytes allowed at sender.

MSS: maximum segment size

TCP Congestion Control: details



sender limits transmission:

TCP sending rate:

 roughly: send cwnd bytes, wait RTT for ACKS, then send more bytes


rate
$$\approx \frac{\text{cwnd}}{\text{RTT}}$$
 bytes/sec

```
LastByteSent-
LastByteAcked ≤ min(cwnd, rwnd)
```

 cwnd is dynamic, function of perceived network congestion

TCP Slow Start

- when connection begins, increase rate exponentially until first loss event:
 - initially cwnd = I MSS
 - double cwnd every RTT
 - done by incrementing cwnd for every ACK received
- <u>summary:</u> initial rate is slow but ramps up exponentially fast




TCP: detecting, reacting to loss

- loss indicated by timeout:
 - cwnd set to I MSS;
 - window then grows exponentially (as in slow start) to threshold, then grows linearly
- loss indicated by 3 duplicate ACKs: TCP RENO
 - cwnd is cut in half window then grows linearly
- TCP Tahoe always sets cwnd to 1 (timeout or 3 duplicate acks)

TCP Congestion Window

Q: when should the exponential increase switch to linear?

A: when **cwnd** gets to 1/2 of its value before timeout.




Implementation:

- variable ssthresh
- on loss event, ssthresh is set to 1/2 of cwnd just before loss event

TCP throughput


- avg. TCP throughput as function of window size, RTT?
 - ignore slow start, assume always data to send
- W: window size (measured in bytes) where loss occurs
 - avg. window size (# in-flight bytes) is 3/4 W
 - avg. throughput is 3/4W per RTT

avg TCP thruput =
$$\frac{3}{4} \frac{W}{RTT}$$
 bytes/sec



TCP Fairness


fairness goal: if K TCP sessions share same bottleneck link of bandwidth R, each should have average rate of R/K




Why is TCP fair?

two competing sessions:

- additive increase gives slope of 1, as throughout increases
- multiplicative decrease decreases throughput proportionally



Going deeper: Network Layer




The Network Layer

- 4.1 Overview of Network layer
 - data plane
 - control plane
- 4.2 What's inside a router
- 4.3 IP: Internet Protocol
 - datagram format
 - fragmentation
 - IPv4 addressing
 - network address translation
 - IPv6

Network layer

- transport segment from sending to receiving host
- on sending side encapsulates segments into datagrams
- on receiving side, delivers segments to transport layer
- network layer protocols in every host, router
- router examines header fields in all IP datagrams passing through it



Two key network-layer functions

network-layer functions:

- forwarding (data plane): move packets from router's input to appropriate router output
- •routing (control plane): determine route taken by packets from source to destination
 - routing algorithms

analogy: taking a trip

- forwarding: process of getting through single interchange
- routing: process of planning trip from source to destination

Network service model

Q: What service model for "channel" transporting datagrams from sender to receiver?

example services for individual datagrams:

- guaranteed delivery
- guaranteed delivery with less than 40 msec delay

example services for a flow of datagrams:

- in-order datagram delivery
- guaranteed minimum bandwidth to flow
- restrictions on changes in inter-packet spacing

Network layer service models:

1	Network nitecture	Service Model	Guarantees ?				Congestion
Arch			Bandwidth	Loss	Order	Timing	feedback
	Internet	best effort	none	no	no	no	no (inferred via loss)
	ATM	CBR	constant	yes	yes	yes	no
			rate				congestion
·	ATM	VBR	guaranteed	yes	yes	yes	no
			rate				congestion
	ATM	ABR	guaranteed minimum	no	yes	no	yes
	ATM	UBR	none	no	yes	no	no

Outline


- 4.1 Overview of Network layer
 - data plane
 - control plane

4.2 What's inside a router

- 4.3 IP: Internet Protocol
 - datagram format
 - fragmentation
 - IPv4 addressing
 - network address translation
 - IPv6

Router architecture overview

high-level view of generic router architecture:





Juniper MX2020

Support 1920 10Gbps Ethernet ports

Overall capacity of 32 Tbps

Destination-based forwarding

forwarding table						
Destination	Link Interface					
through		00010000 00010111		0		
through		00011000 00011000		1		
through		00011001 00011111		2		
otherwise				3		

Q: but what happens if ranges don't divide up so nicely?

Longest prefix matching

longest prefix matching

when looking for forwarding table entry for given destination address, use *longest* address prefix that matches destination address.

Destination Address Range	Link interface
11001000 00010111 00010*** *****	0
11001000 00010111 00011000 *****	1
11001000 00010111 00011*** *****	2
otherwise	3

examples:

DA: 11001000 00010111 00010110 10100001

DA: 11001000 00010111 00011<mark>000 10101010</mark>

which interface? which interface?

Longest prefix matching


- It needs to be done fast, in hardware.
- Longest prefix matching: often performed using ternary content addressable memories (TCAMs)
 - content addressable: present address to TCAM: retrieve address in one clock cycle, regardless of table size
 - Cisco Catalyst: can up ~IM routing table entries in TCAM

Outline


- 4.1 Overview of Network layer
 - data plane
 - control plane
- 4.2 What's inside a router
- 4.3 IP: Internet Protocol
 - datagram format
 - fragmentation
 - IPv4 addressing
 - network address translation
 - IPv6

The Internet network layer

host, router network layer functions:



IPv4 datagram format



Outline


- 4.1 Overview of Network layer
 - data plane
 - control plane
- 4.2 What's inside a router
- 4.3 IP: Internet Protocol
 - datagram format
 - fragmentation
 - IPv4 addressing
 - network address translation
 - IPv6


IP addressing: introduction

IP address: 32-bit identifier for host, router interface

interface: connection between host/router and physical link

- router's typically have multiple interfaces
- host typically has one or two interfaces (e.g., wired Ethernet, wireless 802.11)
- IP addresses associated with each interface






Subnets

■ IP address:

- subnet part high order bits
- host part low order bits
- what 's a subnet ?
 - device interfaces with same subnet part of IP address
 - can physically reach each other without intervening router




network consisting of 3 subnets

Subnets

recipe

- to determine the subnets, detach each interface from its host or router, creating islands of isolated networks
- each isolated network (group of interfaces) is called a subnet




subnet mask: /24

Subnets

how many?

6



IP addressing: CIDR

CIDR: Classless InterDomain Routing

- subnet portion of address of arbitrary length
- address format: a.b.c.d/x, where x is # bits in subnet portion of address



200.23.16.0/23

IP addresses: how to get one?

Q: How does a host get IP address?


- hard-coded by system admin in a file
 - Windows: control-panel->network->configuration->tcp/ip->properties
 - UNIX: /etc/rc.config
- DHCP: Dynamic Host Configuration Protocol: dynamically get address from as server
 - "plug-and-play"

DHCP: Dynamic Host Configuration Protocol


goal: allow host to dynamically obtain its IP address from network server when it joins network

- can renew its lease on address in use
- allows reuse of addresses (only hold address while connected / "on")
- support for mobile users who want to join network


DHCP client-server scenario



DHCP client-server scenario



DHCP client-server scenario




DHCP: more than IP addresses

DHCP can return more than just allocated IP address on subnet:

- address of first-hop router for client
- name and IP address of DNS sever
- network mask (indicating network versus host portion of address)


Hierarchical addressing: route aggregation

hierarchical addressing allows efficient advertisement of routing information:



IP addressing: the last word...

- Q: how does an ISP get block of addresses?
- A: ICANN: Internet Corporation for Assigned Names and Numbers http://www.icann.org/
 - allocates addresses
 - manages DNS
 - assigns domain names, resolves disputes




all datagrams leaving local network have same single source NAT IP address: 138.76.29.7, different source port numbers datagrams with source or destination in this network have 10.0.0/24 address for source, destination (as usual)

motivation: local network uses just one IP address as far as outside world is concerned:

- range of addresses not needed from ISP: just one IP address for all devices
- can change addresses of devices in local network without notifying outside world
- can change ISP without changing addresses of devices in local network
- devices inside local net not explicitly addressable,
 visible by outside world (a security plus)

implementation: NAT router must:

- outgoing datagrams: replace (source IP address, port #) of every outgoing datagram to (NAT IP address, new port #)
 ... remote clients/servers will respond using (NAT IP address, new port #) as destination addr
- remember (in NAT translation table) every (source IP address, port #) to (NAT IP address, new port #) translation pair
- incoming datagrams: replace (NAT IP address, new port #) in dest fields of every incoming datagram with corresponding (source IP address, port #) stored in NAT table



- I6-bit port-number field:
 - 60,000 simultaneous connections with a single LAN-side address!
- NAT is controversial:
 - routers should only process up to network layer
 - address shortage should be solved by IPv6
 - violates end-to-end argument
 - NAT possibility must be taken into account by app designers, e.g., P2P applications
 - Technical solutions: search for "NAT traversal"

Outline

- 4.1 Overview of Network layer
 - data plane
 - control plane
- 4.2 What's inside a router
- 4.3 IP: Internet Protocol
 - datagram format
 - fragmentation
 - IPv4 addressing
 - network address translation
 - IPv6

IPv6: motivation

- initial motivation: 32-bit address space soon to be completely allocated.
- additional motivation:
 - header format helps speed processing/forwarding
 - header changes to facilitate QoS

IPv6 datagram format:

- fixed-length 40 byte header
- no fragmentation allowed

IPv6 datagram format

priority: identify priority among datagrams in flow flow Label: identify datagrams in same "flow." (concept of flow not well defined). next header: identify upper layer protocol for data

ver pri flow label
payload len next hdr hop limit
source address
(128 bits)
destination address
(128 bits)


data

Other changes from IPv4


- checksum: removed entirely to reduce processing time at each hop
- options: allowed, but outside of header, indicated by "Next Header" field
- ICMPv6: new version of ICMP
 - additional message types, e.g. "Packet Too Big"
 - No fragmentation in the intermediate routers. Sender receives "Packet Too Big" and resend smaller datagrams.

Transition from IPv4 to IPv6


- not all routers can be upgraded simultaneously
 - no "flag days"
 - how will network operate with mixed IPv4 and IPv6 routers?
- tunneling: IPv6 datagram carried as payload in IPv4 datagram among IPv4 routers



Tunneling



Tunneling



IPv6: adoption

- Google: 8% of clients access services via IPv6
- NIST: I/3 of all US government domains are IPv6 capable
- Long (long!) time for deployment, use
 - •20 years and counting!
 - •think of application-level changes in last 20 years: WWW, Facebook, streaming media, Skype, ...

Summary: Network Layer Data Plane

- 4.1 Overview of Network layer: data plane and control plane
- 4.2 What's inside a router
- 4.3 IP: Internet Protocol
 - datagram format
 - fragmentation
 - IPv4 addressing
 - NAT
 - IPv6

Question: how do forwarding tables (destination-based forwarding) or flow tables (generalized forwarding) computed?

Answer: by the control plane (next

Answer: by the control plane (next chapter)